

# Workstation 8 and ESXi 5

## available guestOS = ? settings

As far as I know the list of working guestOS settings for virtual Hardware 8 looks like this

```
guestOS = "asianux3"  
guestOS = "asianux3_64"  
guestOS = "centos"  
guestOS = "centos64"  
guestOS = "darwin"  
guestOS = "darwin10"  
guestOS = "darwin10_64"  
guestOS = "darwin11"  
guestOS = "darwin11_64"  
guestOS = "darwin64"  
guestOS = "debian4"  
guestOS = "debian4_64"  
guestOS = "debian5"  
guestOS = "debian5_64"  
guestOS = "dos"  
guestOS = "eComStation"  
guestOS = "eComStation2"  
guestOS = "freebsd"  
guestOS = "freebsd64"  
guestOS = "mandriva"  
guestOS = "mandriva64"  
guestOS = "netware4"  
guestOS = "netware5"  
guestOS = "netware6"  
guestOS = "nld9"  
guestOS = "oes"  
guestOS = "openServer5"  
guestOS = "openServer6"  
guestOS = "oracleLinux"  
guestOS = "oracleLinux64"  
guestOS = "os2"  
guestOS = "other"  
guestOS = "other24xLinux"  
guestOS = "other24xLinux64"  
guestOS = "other26xLinux"  
guestOS = "other26xLinux64"  
guestOS = "other64"  
guestOS = "otherLinux"  
guestOS = "otherLinux64"  
guestOS = "redhat"  
guestOS = "rhel2"  
guestOS = "rhel3"  
guestOS = "rhel3_64"  
guestOS = "rhel4"  
guestOS = "rhel4_64"
```

## Workstation 8 and ESXi 5

guestOS = "rhel5"  
guestOS = "rhel5\_64"  
guestOS = "rhel6"  
guestOS = "rhel6\_64"  
guestOS = "sles"  
guestOS = "sles10"  
guestOS = "sles10\_64"  
guestOS = "sles11"  
guestOS = "sles11\_64"  
guestOS = "sles64"  
guestOS = "solaris10"  
guestOS = "solaris10\_64"  
guestOS = "solaris11\_64"  
guestOS = "solaris6"  
guestOS = "solaris7"  
guestOS = "solaris8"  
guestOS = "solaris9"  
guestOS = "suse"  
guestOS = "suse64"  
guestOS = "turboLinux"  
guestOS = "turboLinux64"  
guestOS = "ubuntu"  
guestOS = "ubuntu64"  
guestOS = "unixWare7"  
guestOS = "vista"  
guestOS = "vmkernel"  
guestOS = "vmkernel5"  
guestOS = "win2000AdvServ"  
guestOS = "win2000Pro"  
guestOS = "win2000Serv"  
guestOS = "win31"  
guestOS = "win95"  
guestOS = "win98"  
guestOS = "windows7Server64"  
guestOS = "windows8"  
guestOS = "windows8\_64"  
guestOS = "windows8Server64"  
guestOS = "winLonghorn"  
guestOS = "winLonghorn64"  
guestOS = "winMe"  
guestOS = "winNetBusiness"  
guestOS = "winNetDatacenter"  
guestOS = "winNetDatacenter64"  
guestOS = "winNetEnterprise"  
guestOS = "winNetEnterprise64"  
guestOS = "winNetStandard"  
guestOS = "winNetStandard64"  
guestOS = "winNetWeb"  
guestOS = "winNT"

# Workstation 8 and ESXi 5

guestOS = "winVista"

guestOS = "winVista64"

guestOS = "winXPHome"

guestOS = "winXPPro"

guestOS = "winXPPro64"

Unique solution ID: #1136

Author: Ulli Hankeln

Last update: 2011-11-09 16:00